Respiratory Protection





1

Objectives

- Principles of respiratory protection
 - History
 - Role
 - Regulations and guidance
 - Equipment
 - Fit Testing
 - Selection and use
 - Programs (WA State)

2

History

- · Animal bladders used in Roman mines
- · Atmosphere-supplying devices in 1700's
- Activated charcoal discovered (1854)
- · World War I "Gas Masks"


3

Atmosphere-Supplying Respirators

Atmosphere-supplying respirator technology was well developed by the 1700's







Respiratory protection

OSHA's general policy on respirator use:

- Where engineering or administrative controls are not feasible or insufficient
- During the time when engineering or administrative controls are being implemented
- · For emergency response situations

6

Role in Exposure Control

- "Hierarchy of Controls"
 - PPE is the least desirable method of control
- Respirator use involves risk
 Medical use determinations
- Administrative procedures
 - Written program
 - Qualified "program administrator"
- · Many Limitations of respirators
 - Monitoring contaminant levels
 - Fit testing
 - Cost
 - Can leak, wear out, or be the wrong kind
 - Can be hot, uncomfortable and make it hard to see or talk
 - Can be hard to breathe through
 - They are easily removed in contaminated air

When Are Respirators Needed?

- In an oxygen-deficient atmosphere
- •When "Permissible Exposure Limits" are exceeded
- •When required by a pesticide label
- •When needed for infection control
- •When required by company policy

Normally, an oxygen deficiency will only be found in a confined space or a major chemical spill. There are only a few pesticides that have label requirements for respirators. Some employers require their employees to wear respirators as a safety precaution even though they may not be required due to a PEL

8

Oxygen Deficiency

Oxygen deficiency can occur in confined or enclosed spaces, during fires or large chemical releases.

Normal air contains 21% oxygen. An area with oxygen content below 19.5 % is considered "oxygen deficient".

Only a supplied air respirator can protect against the effects of oxygen deficiency.



Regulations and Guidance

- OSHA
 - 29 CFR 1910.134, 1974, 1998
- NIOSH
 - 1976, 1987 "Guide to Industrial Respiratory Protection"
 - 1987 "Respirator Decision Logic"
 - 1995 "42 CFR 84"
- · WISHA
 - WAC 296-842
- ANSI STANDARDS
 - Z88.2-1969, 1980, 1992 (Respiratory Protection)

10

OSHA's Respiratory Protection Program

- 1. Written program
- 2. Selection base on hazards involved
- 3. Operator training
- 4. Reserved (?)
- 5. Cleaning and disinfection of respirators
- 6. Storage of respirators
- 7. Inspection and maintenance of respirators
- 8. Surveillance of worker exposures
- 9. Regular evaluation of respirator program
- 10. Medical evaluation of respirator users
- 11. Use of approved respirators

11

Updated regulations

- · NIOSH changes to respirator equipment approvals
- Substance specific standards sometimes contain unique requirements
- · OSHA finalized new 1910.134 standard in 98
 - Consolidates other standards' requirements
 - Assigned Protection Factors (APF) in 2003/04
 - Some changes in medical qualifications (screening)
 - Fit testing (Quant) required for all tight-fitting respirators
 - Cartridge change out to be based on objective data
 - Respirator administrator required

- TB respirators consolidated in 2003

OSHA Proposes Revised Respiratory Protection Standards

- The Occupational Safety and Health Administration published two proposed rules in the June 6 Federal Register to enhance worker protections from respiratory hazards on the job. OSHA is seeking comments until Sept. 4, 2003, on its proposals to amend the Respiratory Protection Standard to include a new fit testing procedure and incorporate new Assigned Protection Factors (APFs) for respiratory protection programs. The proposed rules are expected to prevent approximately 4,000 injuries and illnesses and prevent about 900 deaths annually from cancer and other chronic diseases.
- In a notice of proposed rulemaking, OSHA proposes to amend the existing Respiratory Protection Standard in order to incorporate Assigned Protection Factors (APFs) as part of a complete respiratory protection program to assist workers and employers in the proper selection of respirators. APFs are numbers that reflect the workplace level of respiratory protection that respirators are expected to provide to employees
- http://www.osha.gov/pls/oshaweb/owadisp.show_doc ument?p_table=FEDERAL_REGISTER&p_id=13749

13

OSHA Respirator Standard

- · Use engineering controls where feasible
- Employer supplies respirators and establishes a program
- Program must be written with work-site specific procedures and elements for required respirator use
- · Program must have an administrator
- Medical evaluations
- · Fit testing for tight-fitting respirators

14

OSHA Respirator Standard

- New procedures where respirator is worn voluntarily (program still required)
- Appropriate selection of respirators NIOSH certification and within certification limits
- Evaluate exposures assume IDLH if unable to evaluate
- · Selection to include sufficient number...to get a good fit
- Change-out of cartridges End of Service Life or "objective data"

OSHA Respirator Standard

Medical evaluations:

- By a "Physician or other licensed health care professional" (PLHCP)
- · Screening questionnaire
- Follow-up examination if any positive answers
- Supply PLHCP with respirator info, work conditions, other PPE, duration and frequency or respirator use, copy of written program and OSHA standard
- Must supply PAPR if negative pressure respirator is unacceptable

16

OSHA Respirator Standard

Additional Medical evaluations required when:

- · Report of related medical signs or symptoms
- PLHCP, supervisor or program administrator informs the employer that a reevaluation is needed
- Information from program, fit-testing suggest need for reevaluation
- Change in workplace increases physiological burden on worker

17

OSHA Respirator Standard

Fit testing:

- Qualitative or quantitative methods used for tight-fitting respirators
- Must be re-fitted when respirator changed and annually
- Qualitative can only be used with fit factors of 100 or less; quantitative required when FF > 100
- Must use methods in Appendix A
- Atmosphere-supplying respirator must be tested when in negative pressure mode

18

OSHA Respirator Standard

Other things ...

- · No facial hair that can interfere with seal
- · User seal test
- Cannot base cartridge change-outs on odor, smell or taste
- · Seal check whenever donning respirator
- In IDLH areas, must have standby outside equipped and trained for rescuing
- · Structural firefighting: 2 in and 2 out (buddy)

Specific Respiratory Protection Stds.

Carcinogens (general) WAC 296-62-07306
Coke Ovens WAC 296-62-0011
Concrete Finishing WAC 296-62-20011
Cotton Dust WAC 296-62-744-4533 see section (6)
DBCP WAC 296-62-07442 see section (8)
Emergency Response WAC 296-824

Ethylene Oxde WAC 298-0-27827
Fine Rigidae WaC 298-0-26407
Fine Rigidae Wa

This is a list of the most frequently used standards with respiratory protection requirements, but it's not a complete list for all WISHA standards. While these requirements are viewed as being "supplemental" to the requirements specified in the main respiratory protection standard, WAC 296-62 Part E, they may, at times, preempt some of the requirements in the main standard if noted.

20

Respirator Equipment

Types of Respirators

Air-purifying respirators – filters air through cartridges or filtering facepieces (dust masks)

Powered air-purifying respirators – PARP filters air through cartridges with assistance of a blower.

 $\label{eq:air-limit} \mbox{Airline respirators} - \mbox{provides unlimited clean air from a compressor.}$

Self-contained breathing apparatus (SCBA) - provides 30-60 minutes of clean air from a tank.

Escape respirators – provides air for escape only from a small bottle.

22

Respirator Terminology

- · Respiratory inlet covering
- · Pressure relative to atmosphere
- Mode of operation

- ANS

23

21

Respiratory Inlet Covering

- Definition
 - That portion of a respirator that forms the protective barrier between the user's respiratory tract and an airpurifying device or breathing air source, or both"
 - ANSI Z88.2-1992OSHA 1910.134 (1998)

Respiratory Inlet Covering

- Mouthpiece
 - Used to escape from a contaminated atmosphere
 - Noseclamps prevent inhaling through nostrils
 Acid-gas mouthpiece "escape" respirators (APR)

 - "Self rescuer" APR
 - » CO catalyst "Hopcalite"
 - » Used to escape from mines Self-Contained Self Rescuer (SCSR)
 - » KO₂ absorbs CO₂ and releases O₂





Respiratory Inlet Covering

- Quarter-Face
 - Extend bridge of nose to front of chin
 - Popular in mining industry
 - Replaceable filter element



Respiratory Inlet Covering

- Half-Face
 - Bridge of nose to bottom of chin
 Variety of sizes

 - Usually negative-pressure APR
 Filtering facepiece
 Avoid using non-NIOSH approved dust masks



Respiratory Inlet Covering

- Full Facepiece
 - Better "fit" (and protection)
 - Variety of sizes
 - Eye protection
 - Eyeglasses?
 - "Dead Air" issues
 - "Nosecup" recommended



Respiratory Inlet Covering

- Hood/Helmet
 - Loose fitting"
 - Welding
 - Abrasive Blasting "Type CE"







29

Operating Pressure

- Negative pressure
 - Pressure drops below atmosphere when user inhales
 - Less protective due to facepiece leaks
- Positive pressure
 - Pressure above atmosphere
- **Pressure Demand**
 - Elevated pressure at all times
 - Most protective suitable for IDLH

30

Mode of Operation

- · Air-Purifying Respirators (APRs)
 - Contaminants removed from the air
 - » Filters for removing particulates
 - » Cartridges for removing gases or vapors may have filters, too

 - » Canisters (used with "gas masks" -- large capacity)
 - » Oxygen must be > 19.5%
 - Limited protection
- Atmosphere-supplying respirators
 - Not limited by type of atmospheric hazard
 - Suitable for oxygen deficiency or IDLH
 - SCBA's
 - Air line respirators (Type C or CE)
 - Combinations of SCBA's and SAR's

- **Respirator Types**
 - Negative pressure
 » Mouthpiece
 - » Quarter-, half-, full-facepiece

 - Positive pressure

 » Powered Air Purifying Respirator (PAPR) » Less physiological stress,
 - Specified in many OSHA standards
 Tight- or loose-fitting models
 - Specialty respirators
 - » Escape (mouthpiece, "gas mask")
 - » Welding





Some types of Air-purifying Respirators



Filtering faceniece (dust mask)



Full-face cartridge respirator



Half-face cartridge respirator



Powered air-purifying respirator

Aerosol removing respirators

Filters can remove dusts, mists, fumes, others Cannot protect against gases, vapors, or low O² Removal mechanisms:

- · interception
- sedimentation
- impaction
- diffusion
- electrostatic attraction

34

Nine filter types

- · 3 levels of filter efficiency:
 - -95% (called "95")
 - -99% (called "99")
 - -99.97% (called "100")
- 3 categories of resistance to filter efficiency degradation:
 - N (Not resistant to oil)
 - -R (Resistant to oil)
 - -P (oil Proof)

35

Selection of N, R, and P-series filters

- If no oil particles are present in the work environment, use a filter of any series.
- If oil particles are present, use an R- or P-series filter
- If oil particles are present and the filter is to be used for more than one work shift, use only a P-series filter.
- Selection of filter efficiency depends on how much filter leakage can be accepted.
- Choice of face piece depends on level of protection needed (APF).

Gas and vapor removing respirators

Use sorbents

Housed in cartridges or canisters

Removal mechanisms:

- adsorption
- absorption
- chemisorption
- catalysis

Designed for specific contaminants or classes

Gas and vapor removing cartridges

Organic vapor cartridges:

- currently tested with CCI₄ at 1000 ppm (only)
- · may or may not be very effective for specific vapors
- seek guidance from respirator manufacturer including test data on vapor in use
- · only small amount of charcoal in cartridges
- · more charcoal in canisters
- · color code: black

Service life of cartridges or canisters

Depends on:

- · quality and amount of sorbent
- · packing uniformity and density
- · exposure conditions, breathing rate
- relative humidity
- · temperature
- · contaminant concentration
- · affinity of the gas or vapor for the sorbent
- · presence of other gases and vapors

39

37

Acid gas respirators

- · Designed for removing acidic gases
- Tested by NIOSH against chlorine, HCl and SO₂ (only)
- · Limited to fairly low concentrations

 - Chlorine
 10 ppm

 - Hydrogen chloride
 50 ppm

 - Sulfur dioxide
 50 ppm

· Color code: white

40

Alkaline gas cartridges

- Contains chemicals for removing alkaline gases such as:
 - ammonia
 - methylamine
- · Concentrations limited
 - ammonia 300 ppmmethylamine 100 ppm
- · Color code: green

41

Air-purifying respirators additional information

- · Replace cartridges:
 - NIOSH: daily or after each use, or even more often if odor, taste, or irritation
 - some canisters may have end of service life indicators
- · Other cartridges available:
 - pesticides
 - carbon monoxide
 - ethylene oxide
 - formaldehyde
 - hydrogen fluoride
 - hydrogen sulfide
 - mercury
 - phosphine
 - vinyl chloride

42

Colors for AP elements

Acid gas	white
Organic vapors	black
Ammonia gas	green
Carbon monoxide	blue
 Acid gases and organic vapors 	yellow
 Acid gas, ammonia, and OV 	brown
 Acid gas, ammonia, CO, and OV 	red
 Other vapors and gases 	olive
 Radioactive materials (HEPA) 	purple *
 Dusts, fumes, mists (non-radio) 	orange *

43

"Adequate warning properties"

NIOSH permits air purifying respirators only if the contaminant has adequate warning properties:

- reliable detection of the contaminant below the PEL by user's sense of smell, taste, or irritation
- only applies to gases and vapors -- not particulate
- Exception is if AP element has an ESLI.

standard)

- Remember that odor thresholds vary substantially from one individual to another
- OSHA: respirator cartridge *changeout* based on odors or taste unacceptable (new

Atmosphere-supplying respirators

- · Self-contained breathing apparatus (SCBA)
- · Supplied Air Respirators or Air-line (called "Type C" or "Type CE")
 - hose can be up to 300 feet
 - 4 cfm required for tight-fitting mask, 6 cfm for hoods and helmets
 - available in demand, pressure demand, and continuous flow arrangements
- Combination SCBA and SAR

Must be supplied with Grade D breathing air, usually from bottles or compressors

45

Atmosphere-Supplying Respirators

- Self-Contained Breathing Apparatus (SCBA)
 - Pressure-demand, open circuit
 » 30 to 60 minute duration
 - » 2216 or 4500 PSI

 - Demand (virtually obsolete)Closed circuit "rebreather"
 - » Up to 4 hours duration
 - » Used for mine rescue, etc.
 - » O₂ from cylinder or generator
 - » CO₂ is absorbed





46

Self-contained breathing apparatus (2)

- · Open-circuit type
 - bottled air from 2000 to 4500 psi typically
 - time from 15 min to 60 min typically
 - demand or pressure demand or continuous flow
 - can be combined with supplied air respirator
 - escape-only type available in 5, 7, 10 or 15 minute size
- · Closed-circuit type (also called re-breathers)
 - could be either negative or positive pressure type
 - possible to "over breathe"
 - more complicated to maintain
 - requires more training
 - longer use period ... sometimes up to 4 hours

Atmosphere-Supplying Respirators

- Supplied Air Respirators (SAR)
 - Also known as "airline" respirators or "Type C"
 - Supplied with compressed air
 » 4-6 CFM
 - Pressure of operation » Pressure demand
 - » Demand

 - Combination
 - » APR
 - » SCBA (for IDLH)





Atmosphere-Supplying Respirators

- · Air Quality "Grade D" minimum (1910.134)
- · Compressor provisions for air quality
 - air intake location
 - dew point 10 F below ambient

 - sorbent bed and filters maintained
 CO and/or high temperature alarm
 - incompatible fittings
- Cylinders maintained and tested
- "Certificate of analysis", cylinders marked
 -50 F dewpoint



49

Grade D Specifications

CGA G-7.1 Grade "D" (Compressed Gas Association)			
Oxygen	19.5 - 23.5%		
Carbon Dioxide	1,000 ppm		
Carbon Monoxide	10 ppm		
Oil Mist	5 mg/m_		
Odor	"no pronounced odor"		

50

Sources of breathing air

- Compressors
 - Subject to failure
 - If oil-lubricated, can overheat changing oil mist into CO
 - Carbon vane type are available and oil-less
 - Can run continuously
 - Can be fitted with CO sensor and/or adsorption units
 - Air intake location is critical
- Compressed gas cylinders (breathing air)
 - Can be up to 3500 psi
 - Finite air supply...for limited time spans
 - Do not rely on utility services

51

Protection Factors

BREAK!

Protection factors

- protection factor: $PF = C_o/C_i$ O for outside the mask, I for inside the mask
- · Penetration efficiency is inversely related:
 - Used to average PF values

$$P_e = \frac{1}{PF}$$

- Fit factor is the PF observed during a quantitative fit test (usually only 5 to 10 min)
- Workplace protection factor (WPF)
 - time up to 8 hours
 - the C_i value is the average contaminant value inside the respirator
 - the $\mathbf{C}_{\mathbf{0}}$ value is the average contaminant value outside the respirator

53

Protection Factors

- "Protection factors" are related to the amount of contaminant that gets into a respirator
 - Generic PF = Conc. outside / conc. inside
- Assigned Protection Factor (APF)
- Minimum anticipated protection for a specific type
 Used to established respirator safe use limits
- Recommended by OSHA, 2003 (not addressed by 1910.134 in 1998)
- Established by NIOSH, ANSI
- · Assigned protection factor APF (also called hazard ratio)

Assigned Protection Factor (APF) $\left[\text{Expected} \, \frac{C_{\circ}}{C_{i}} \right]$

NIOSH Assigned Protection Factor (APF)

Respirator type	APF
Quarter face	5
Half-face APR or "demand" supplied air	10
Hood or helmet PAPR or continuous flow	25
Full-Face APR or "Demand" supplied air, any tight- fitting facepiece PAPR or continuous	50
Half-face pressure demand	1000
Full-face pressure demand	2000
SCBA pressure demand	10000

55

Assigned Protection Factor (APF), from ANSI Z88.2-1992

Respirator type		Inlet covering				
		mask, 1/4 mask	full face-piece	Helmet, hood	Loose-fitting facepiece	
Air purifying		10	100			
Powered Air Purifying		50	100 or 1000*	1000	25	
supplying - Airline Conti	Demand	10	100			
	Continuous flow	50	1000	1000	25	
	Pressure- demand	50	1000	* 1000 APF for high-efficiency filters only		
Atmosphere supplying -	Demand	10	100	1		
SCBA	Pressure- demand		10000	1		

00114	F4		
OSHA proposed Assigned Protection Factors			
Respirator type	APF		
Quarter face	n.a.		
Half-face APR or "demand" supplied air	10		
Hood or helmet PAPR or continuous flow	1000		
Loose-fitting facepiece PAPR or	25		
continuous flow			
Full-Face APR or "Demand" supplied	50		
वांght-fitting full-facepiece, PAPR or	1000		
continuous flow			
Half-face pressure-demand	1000		
Full-face pressure-demand	2000		
SCBA pressure-demand	10,000		

TABLE V-1.—SUMMARY RESULTS FROM WORKPLACE PROTECTION FACTOR (WPF) STUDIES AND ESTIMATED FRE-CUBADLES OF RESIDERATOR FALURE, BASED ON A ORE-FACTOR ANOVA ANALYSIS OF DATA FROM WORKPLACE PRO-TICTION FACTOR (WPF) STUDIES.

	WPT (95% C.I.*)	deviation	MIP	WPF ≤10 ²	VAPF s2 z	5% of the time 3	of the time 3
	Studios Reflecting	Inadequate F	rogram Elen	pends			
Particulate Exposure		1					
Toncy and Barnhart [1972] (Ex. 64-68) Harris et al. [1974] (Ex. 27-11)	*11.4 (3.2–39.6)	44.12	31.1	76.8	9.0	100	60.4
Low Estimate	93.6 (1-17.9)	52-93	6.4	99.7	38.8	100	96.4
High Estimate	65.7 (1.6-20.4) 65.6	*2.93	10.2	97.0	12.5	100	82.5
Moore and Smith (1976) (Ex. 64-69)							
Respirator A	15.29 (8.3-28.1)	72.36	22.1	35.2	< 0.01	98.9	1.5
Respirator B	13.72 (7.7-24.4)	72.15	18.4	41.3	< 0.01	99.7	0.5
Respirator C	9.59 (4.8-19.2)	72.16	12.9	83.1	< 0.01	100	9.0
Toney and Barnhart [1972] (Ex. 64-68) Weighted Geometric Mean	43.8 (1.2-11.9) 49.4	42.28	5.3	100	14.7	100	96.7
	Studies Reflect	ing Good Pro	gram Elemen	ifs			
Particulate Exposure		1					
Dixon and Nelson (1984)*	3360 (3101-3640)	4.8	11 498	<0.01	<0.01	<0.01	<0.0
Gaboury and Burd [1989]*	47 (31-72)	2.5	72	0.2	<0.01	30.1	<0.0
Lenhart and Campbell [1984]*	166 (120-228)	3.8	405	0.1	< 0.01	9.0	0.0
Nelson and Dixon [1985]*	258 (192-347)	5.2	1004	0.7	< 0.01	14.5	0.3
Gosselink et al. [1985]*	96 (75-123)	2.3	136	<0.01	< 0.01	0.1	<0.0
Cotton and Mullins [1992]*	147 (117-185)	2.5	224	< 0.01	< 0.01	0.1	<0.0
Myers [1990]* Weighted Geometric Mean	346 (256-468) 5142	7.2	2,428	2.8	0.1	22.2	1.7
Gas/Vapor Exposure							
Galvin et al. [1990] (Ex. 64-22)	79 (54-115)	3.5	173	1.1	< 0.01	31.7	0.2

To by Companies sterind or the generator reads in VP - conclusion as shows the structureous condender interest; ypb-vivi. L₁ = 0.0, which is 1 th is murked of stated being companie (i.e., 10 for particulate studies value) in 1 th in the control of the second of the stated studies.
**Calculated from equation 0 as descrated in the text, v = 0, 1 or VPF = 10, a = 0.5 to VPF = 2.
**Calculated from equation 0 as descrated in the text, v = 0, 1 or VPF = 10, a = 0.5 to VPF = 2.
**Calculated from equation 0 as descrated in the text, v = 0, 1 or VPF = 0, a = 0.5 to VPF = 2.
**Fasing or VPF values desirable by Prince of the text, v = 0, 1 or VPF = 0, a = 0.5 to VPF = 2.
**Fasing or VPF values desirable by Prince of the text, v = 0, 1 or VPF = 0, a = 0.5 to VPF = 2.
**Calculated from equation 0 to the text, v = 0, 1 or VPF = 0, a = 0.5 to VPF = 2.
**Calculated from equation 0 to the text, v = 0, 1 or VPF = 0, a = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 2.
**Calculated from equation 0 to VPF = 0.5 to VPF = 0.
**Calculated from equation 0 to VPF = 0.5 to VPF = 0.
**Calculated from equation 0 to

57

Protection Factors

- - Measured during fit testing procedures

Quantitative Fit Factor (QNFF)

- Workplace Protection Factor
 - Measured under workplace conditions

Workplace Protection Factor (WPF) $\left[\frac{\textbf{C}_{\circ}}{\textbf{C}_{i}}\right]$

59

Protection Factors

- Effective protection factor
 - Includes times when the worker is not wearing the respirator

Effective Protection Factor (EPF) $\left[\frac{C_o}{C_{inhaled}}\right]$

- over unspecified length of time
 supposed to represent total protection afforded worker including times worn and not worn.
 Used in OSHA's lead standard
- Program protection factor
 - sometimes used with lead aerosols

Maximum Use Concentration

- · Maximum Use Concentration, MUC
 - Not currently defined by OSHA, although many standards incorporate the general principle
 - Usually defined as the PEL x APF
 - must not be > IDLH or in excess of the cartridge limits
 - Based on several factors: APF, IDLH concentrations, and regulatory limits
 - Example
 - » APF for half mask = 10
 - » PEL for lead = 0.05 mg/m³
 - » MUC = 10 x 0.05 mg/ = 0.5 mg/m³

61

RESPIRATOR FIT

- User "seal checks" (formerly "fit checks")
 Each time the respirator is worn

 - Positive- and negative-pressure (OSHA)
 - Odorous or irritant agents may be used (ANSI)
- Fit Testing
 - Formal test, to select respirator sizes and models

 - » Involves several "exercises" » Initial fit testing, before the respirator is issued
 - » Repeated annually
 - Subject is exposed to a challenge atmosphere
 » Qualitative tests (taste, odor, irritation)

 - » Quantitative tests (instrumentation)

62

Fit Testing Requirements

- · Previously, OSHA only required fit testing for negative pressure respirators
- Since 1998, all tight-fitting respirators must be fit tested
 - Negative pressure respirators
 - » Qualitative testing for half-face
 - » Quantitative testing for full-face (where 500 FF is desired)
 - Positive pressure respirators
 - » Must be tested in the negative-pressure mode
 - Modify respirator for negative pressure operation, or use a "surrog respirator
 - » Quantitative or qualitative testing is acceptable

63

Fit testing

- · Qualitative fit testing (QLFTs)
 - isoamyl acetate (IAA)
 - irritant smoke (usually titanium and stannic chloride)
 - saccharin aerosol (taste test)
 - denatonium benzoate (Bitrex)
 - must verify wearer can respond
 - wearer must be truthful
- · Quantitative fit testing (QNFTs)
 - dioctyl phthalate aerosol (DOP)
 - corn oil
 - sodium chloride
 - DEHS
 - ambient air (with submicron particulate counting)
 - ambient air (pressure differential)

Qualitative Fit Testing

- · OSHA accepts 4 qualitative protocols
 - Isoamyl acetate (banana oil)
 Saccharine

 - Bitrex
 - Irritant smoke
- Outcome depends on subject's response
- Strong subject incentive to "pass" the test Results may not be reliable
- · Pass criteria is based on 100 Fit Factor
 - This provides a 10x safety factor for APF 10

65

Qualitative Fit Testing

- Saccharine
 - Particulate filter APRs, including dust masks
 - Hood
 - Sensitivity test
 - Challenged with 100 x solution
- Bitrex
 - Denatonium benzoate
 - Same equipment



Qualitative Fit Testing

- · Isoamyl Acetate (IAA, "banana oil")
 - Sensitivity test
 - APRs with organic vapor cartridges
- IAA saturated paper towel inside hood
- Irritant smoke (stannic chloride)
- Not for persons with asthma!
- No hood or enclosure APR with high-efficiency filters
- Safety concerns



Quantitative Fit Testing

- Quantitative fit testing uses probed respirators (or adapters) to measure inside the facepiece
- "Fit factor" is determined from the leak rate.
 - Previously, fit testing was used to determine a "Personal protection factor" (ANSI 1980)
 - Now, criteria includes a 10x safety factor (ANSI 1992, OSHA)
 - » Measured Fit Factor must be at least 10x the Assigned Protection Factor to accept a facepiece





Quantitative Fit Testing

- OSHA accepts 3 quantitative protocols Generated aerosol method

 - » Old technology
 - Condensation Nuclei Counter (CNC)

 » Ambient air challenge atmosphere

 - Controlled negative pressure » Measures actual leakage







Quantitative Fit Testing

- Fit factor calculations
 - Fit factors for each exercise are combined

Overall Fit Factor = $\overline{1/ff_1+1/ff_2+1/ff_3+1/ff_4+1/ff_5+1/ff_7+1/ff_8}$

> Where ff_1 , ff_2 , ff_3 , etc. are the fit factors for exercises 1, 2, 3, etc.

> > 70

Respirator selection

Routine use vs non-routine use Workplace hazards **Physical Characteristics** Physical demands of the work Respirator capabilities and limitations

Selection: Exposure assessments

- · Identify airborne contaminants where possible
- · Match up specifications and limitations of respirators
- · Consider abnormal conditions that may cause concentrations to rise
- · Think in terms of "worst case" exposures
- · Apply substance-specific requirements
- · Communicate information to employees; discuss signs, symptoms of overexposure
- · Keep good records

72

Determining physical state of airborne contaminant

Listing of contaminant in TLV book is a clue but there are some exceptions

Guidelines for estimating airborne phase have been developed based on:

- · identity of the major constituents
- saturated vapor concentrations of constituents
- estimate of total airborne mass concentration (the saturated vapor concentration and total airborne concentration can help predict phase)

73

Selection: Non-routine use of respirators

Three situations require careful consideration:

- · entry into confined spaces
- · entry into oxygen-deficient atmospheres
- · emergencies

IDLH

ANSI: "...any atmosphere that poses an immediate, irreversible debilitating effects on health..." (acute effects vs chronic exposures)

OSHA standard requires atmospheres to be considered IDLH unless shown otherwise

74

Selection: IDLH, continued

NIOSH: IDLH based on two factors:

- worker must be able to escape within 30 min without losing life or suffering permanent health damage, and
- worker must be able to escape without severe eye or respiratory irritation or other reactions that could inhibit escape

also, atmospheres > LEL are IDLH

75

Respirator Selection Conditions Type of Respirator IDLH conditions or oxygen deficiency SCBA or airline respirator with escape bottle Dust/chemical levels up to 1000 times PEL Airline respirator with full facepiece or hood Dust/chemical levels up to 100 times PEL Air-purifying respirator with full facepiece Dust/chemical levels up to 50 times PEL Powered air purifying respirator with half facepiece Dust/chemical levels up to 10 times PEL Air-purifying respirator with half facepiece

NIOSH respirator decision logic

IDLH atmospheres -- Only 2 types allowed:

- SCBA in pressure-demand mode (≥15 minute air supply)
- Type C airline respirator, pressure-demand or continuous flow mode, with auxiliary escape bottle (minimum service life of 3 minutes)

IDLH atmospheres (low oxygen)

- Can use demand (negative pressure) airline respirator

77

Respirator Approval

- Respirators approved by NIOSH
 - Previously NIOSH/MSHA (30 CFR part 11)
 - NIOSH 42 CFR 84, since 1995
- Manufacturers submit respirators to NIOSH
- Each respirator configuration is approved
 - Includes:
 - » Airline hose diameter and length (up to 300 ft.)
 - » Air pressure (up to 125 psi)
 - » Cartridges
- Any change voids the approval
- NIOSH Certified Equipment List
 - Previous documents contained useful information
 - Current document is little more than a list of manufacturers and approval numbers.
 - http://www.cdc.gov/niosh/celpamp.html

78

NIOSH/MSHA certification

- Testing and certification codes issued (TC #)
- · NIOSH personnel do actual testing
- · List of approved respirators published

• TC 13F + 2-3 digits SCBA

• TC 14G + 2-3 digits AP gas mask

• TC 19C + 2-3 digits SAR

TC 21C + 2-3 digits
 TC 23C + 2-3 digits
 Particulate AP
 Gas or vapor AP

70

What is required in a respirator program?

- ✓ Respirator program administrator
- ✓ Written procedures and records
- \checkmark Proper respirator selection
- ✓ Medical evaluation of respirator users
- ✓ Fit-testing of respirators to each user
- \checkmark Respirator maintenance, repair & storage
- √ Assured air quality for supplied-air respirators
- ✓ Employee training

Written Respirator Program

Prepared materials:

- from manufacturers
- From WISHA sample program
- Other boiler plate programs

Must be workplace-specific



Link to sample written respirator program

Much of your written program can be composed of compiled procedures from several source But some procedures will need to reflect your specific workplace practices. Be careful of "boiler plate" programs which may not des

Voluntary Respirator Use

If you allow employees to wear respirators:


- Provide the mandatory handout (link below),
- ensure safe use,
- provide medical evaluations
- ensure proper cleaning, storage and maintenance

http://www.lni.wa.gov/wisha/rules/generaloccupational health/HTML/62E_1.htm#WAC296-62-07117

These requirements apply to voluntary use of all respirators including dust masks. Fit-testing is not required.

WISHA Respirator Regulations

WAC 296-842.



http://www.lni.wa.gov/wisha/Rules/respirators/default.htm

